
Print to AccuRoute[®] Installation Guide

January 2013



Omtool, Ltd.

6 Riverside Drive
Andover, MA 01810
Phone: +1/1 978 327 5700
Toll-free in the US: +1/1 800 886 7845
Fax: +1/1 978 659 1300

Omtool Europe

25 Southampton Buildings
London
WC2A 1AL
United Kingdom
Phone: +44/0 20 3043 8580
Toll-free in the UK: +44/0 80 0011 2981
Fax: +44/0 20 3043 8581

Web: <http://www.omtool.com>

© 2013 by Omtool, Ltd. All rights reserved. Omtool, AccuRoute and the Company logo are trademarks of the Company. Trade names and trademarks of other companies appearing in this document are the property of their respective owners.

Omtool product documentation is provided as part of the licensed product. As such, the documentation is subject to the terms outlined in the End User License Agreement. (You are presented with the End User License Agreement during the product installation. By installing the product, you consent to the terms therein.)

Permission to use the documentation is granted, provided that this copyright notice appears in all copies, use of the documentation is for informational and non-commercial or personal use only and will not be copied or posted on any network computer or broadcast in any media, and no modifications to the documentation are made. Accredited educational institutions may download and reproduce the documentation for distribution in the classroom. Distribution outside the classroom requires express written permission. Use for any other purpose is expressly prohibited by law.

Omtool and/or its suppliers make no guaranties, express or implied, about the information contained in the documentation. Documents and graphics contained therein could include typographical errors and technical inaccuracies. Omtool may make improvements or changes to the documentation and its associated product at any time.

Omtool support and sales

Online resources

The Omtool web site provides you with 24-hour access to documentation, software updates and other downloads, and detailed technical information that can help you troubleshoot issues. Go to <http://www.omtool.com/support> and log in using your customer number. Then click one of the following:

- **Knowledge Base** to access technical articles.
- **Downloads & Docs** to access online documentation, software updates, and downloads.

Customer service and technical support

Contact Omtool Customer Service or Technical Support using any of the following methods:

- **Phone:** +1/1 978 327 6800 or +1/1 888 303 8098 (toll-free in the US)
- **Fax:** +1/1 978 659 1301
- **E-mail:** customerservice@omtool.com or support@omtool.com

Technical support requires an active support contract. For more information, go to <http://www.omtool.com/support/entitlements.cfm>.

Sales, consulting services, licenses, and training

Contact Omtool Sales using any of the following methods:

- **Phone:** +1/1 978 327 5700 or +1/1 800 886 7845 (toll-free in the US)
- **Fax:** +1/1 978 659 1300
- **E-mail:** sales@omtool.com

Contents

Section 1: Introduction to Print to AccuRoute

Features	1-1
Requirements	1-1

Section 2: Installation

Installing Print to AccuRoute for the Web Client.....	2-1
Standard Installation	2-1
Silent Mode Installation.....	2-4
Installing Print to AccuRoute for the AccuRoute Desktop.....	2-5
Standard Installation	2-5
Silent Mode Installation.....	2-6

Section 3: Uninstalling Print to AccuRoute

Standard Uninstallation	3-1
Silent Mode Uninstallation	3-1

Contents

Section I: Introduction to Print to AccuRoute

Features

Print to AccuRoute allows users to print any document to the AccuRoute PDF printer, which makes a .pdf version of that document. Then the system opens the .pdf file in either the AccuRoute Desktop or Web Client, where it is available to be sent to recipients or addresses, just like any other message.

With Print to AccuRoute, users can take advantage of AccuRoute messaging capabilities for file formats not typically supported. The Print to AccuRoute installation offers two choices:

- Print to AccuRoute Desktop
- Print to AccuRoute Web Client

Requirements

Client Requirements

The system where you install one of the Print to AccuRoute v4.0 options must meet the following requirements:

Table I-1: Client Installation Option Requirements

To install	Requires
Print to AccuRoute Desktop	AccuRoute Desktop v4.0
Print to AccuRoute Web Client	AccuRoute Web Client v4.0

Section I: Introduction to Print to AccuRoute

Section 2: Installation

This section describes how to install both of the Client installation options included with the Print to AccuRoute software. You can select only one of these options to install. Each client option has both standard and silent mode installation processes.

This section includes:


[Installing Print to AccuRoute for the Web Client](#) (2-1)

[Installing Print to AccuRoute for the AccuRoute Desktop](#) (2-5)


Installing Print to AccuRoute for the Web Client

Standard Installation


- I Run `Setup.Exe`. The setup opens the **InstallShield Wizard** and the **Welcome** message appears. Click **Next** to begin the installation process.




- The **Document Destination** page appears. Your selection here determines the course of the installation. Select **Upload to Web Client** and click **Next**.




- The **Web Client URL** page appears. Enter the AccuRoute Web Client URL. This is usually: `http://[ServerName]/webclient`



- 4 Click **Next**. The **Ready to Install the Program** page appears. Click **Install** to install the Print to AccuRoute Web Client.



- 5 When installation is complete, the **InstallShield Wizard Completed** message appears. Click **Finish** to close the wizard.



Silent Mode Installation

To install the Print to AccuRoute for AccuRoute Web Client in silent mode:

- 1 Log on to the client with an account that belongs to the local Administrators group.
- 2 Copy the Print to AccuRoute setup directory to a local drive, or map a drive to the folder that contains the setup files.
- 3 Open a command prompt.
- 4 Set the current directory to the Print to AccuRoute setup directory.
- 5 Run: `setup.exe /s /V"/qn ADDLOCAL=WebUploader ACCURROUTE_SERVER=http://ARServer/WebClient"`

where the ARServer is the name of the AccuRoute server.

This installs Print to AccuRoute to the default location, **C:\Program Files\Omtool\Print To AccuRoute**.

To change the location, set the property **INSTALLDIR**. Run: `setup.exe /s /v"/qn INSTALLDIR=<short name path>"` where `<short name path>` is the short name path to the target folder. The entire path must be in short name format.

For example

```
setup.exe /s /V"/qn ADDLOCAL=WebUploader ACCURROUTE_SERVER=http://
ARServer/WebClient INSTALLDIR=J:\PROGRA~1\OMTOOL\ACCURO~1"
```


Tip The command for short name conversions is `dir /x`. Run this command in any directory to return the short names of all folders in that directory. For example, to do a short name conversion on **J:\Program Files**, change the current directory to **J:** and run `dir /x`.

To verify that Print to AccuRoute is installed on the client, go to **Device and Printers** and verify that the AccuRoutePDF printer is installed.


Installing Print to AccuRoute for the AccuRoute Desktop

Standard Installation


- 1 Run **Setup.Exe**. The setup opens the **InstallShield Wizard** and the **Welcome** message appears. Click **Next** to begin the installation process.




- 2 The **Document Destination** page appears. Your selection here determines the course of the installation. Select **Launch AccuRoute Desktop** and click **Next**.



- 3 The **Ready to Install the Program** page appears. Click **Install** to install Print to AccuRoute for the AccuRoute Desktop.



- 4 When installation is complete, the **InstallShield Wizard Completed** message appears.



- 5 Click **Finish** to close the wizard.

Silent Mode Installation

Note The AccuRoute Desktop Client must be installed prior to installing Print to AccuRoute.

To install the Print to AccuRoute for the AccuRoute Desktop in silent mode:

- 1 Log on to the client with an account that belongs to the local Administrators group.
- 2 Copy the Print to AccuRoute setup directory to a local drive, or map a drive to the folder that contains the setup files.
- 3 Open a command prompt.

- 4 Set the current directory to the Print to AccuRoute setup directory.
- 5 Run: `setup.exe /s /V"/qn ADDLOCAL=ARDLauncher"`

This installs Print to AccuRoute to the default location, **C:\Program Files\Omtool\Print To AccuRoute**.

To change the location, set the property **INSTALLDIR**. Run: `setup.exe /s /v"/qn INSTALLDIR=<short name path>"` where `<short name path>` is the short name path to the target folder. The entire path must be in short name format.

For example

```
setup.exe /s /V"/qn ADDLOCAL=ARDLauncher  
INSTALLDIR=J:\PROGRA~1\OMTOOL\ACCURO~1"
```

Tip The command for short name conversions is `dir /x`. Run this command in any directory to return the short names of all folders in that directory. For example, to do a short name conversion on **J:\Program Files**, change the current directory to **J:** and run `dir /x`.

To verify that Print to AccuRoute is installed on the client, go to **Device and Printers** and verify that the AccuRoutePDF printer is installed.

Section 3: Uninstalling Print to AccuRoute

Installation involves two procedures, as described in this section:

[Standard Uninstallation](#) (3-1)

[Silent Mode Uninstallation](#) (3-1)

Standard Uninstallation

To remove **Print to AccuRoute** via the standard uninstallation process:

- 1 In the system **Control Panel** go to **Programs > Programs and Features > Uninstall or change a program**.
- 2 Select **Print to AccuRoute** from the program list.
- 3 Click **Uninstall** at the top of the list.

Silent Mode Uninstallation

To remove the **Print to AccuRoute** in silent mode:

- 1 Log on to the client with an account that belongs to the local Administrators group.
- 2 Copy the Print To AccuRoute setup directory to a local drive, or map a drive to the folder that contains the setup program. (The setup program is required to remove the application silently.)
- 3 Open a command prompt.
- 4 Set the current directory to the Print to AccuRoute setup directory.
- 5 Run: `setup.exe /s /v"/qn REMOVE=ALL"`

This removes Print to AccuRoute from the default location, **C:\PROGRAM FILES\OMTOOL\Print to ACCUROUTE**.

To change the location, set the property **INSTALLDIR**. Run: `setup.exe /s /v"/qn INSTALLDIR=<short name path>"` where **<short name path>** is the short name path to the target folder. The entire path must be in short name format. For example, **J:\PROGRA~1\OMTOOL\ACCURO~1**.

Section 3: Uninstalling Print to AccuRoute